

Configuration File



This page is obsolete and will be reworked soon

- Locus type: **Free/Pro**, 2.3.2+
- Last updated manual: **2.3.2**

Description

- Since version 2.3.2, Locus offer advanced configuration possibilities through *config.cfg* file placed into **root directory of Locus** on your **card/memory**
- This file is manually created when Locus starts for first (if not exist). Data are loaded at start and flushed in the end back to file, so if this file allow changing some settings that are also changeable in the application, settings will not be lost.


Explanations of some parameters

guiding_path_map_symbol

This parameter allows to define very precisely, shape and size of guiding line. Best is to explain it on default parameter.

Basic values are: **-8.0|-2.0|7.0|0.0|-8.0|2.0**

Imagine squared paper. Every two numbers, means X and Y coordinates. So draw them. Result will be as on screen below. With same way, you may draw whatever symbol you want.



Examples of some settings

guiding_path_symbol



guiding_path_symbol=-20|0|-20|-10|0|-10|0|-20|20|0|0|20|0|10|-20|10



guiding_path_symbol=-11|0|-14|-5|5|0|-14|5

map items

keyword	default
map_items_accuracy_circle_color	#0000FF
map_items_dynamic_altitude_font_size	14.0
map_items_dynamic_altitude_color	#FF0000
map_items_dynamic_altitude_color_bg	#FFFFFF
map_items_time_rings_font_size	14.0
map_items_time_rings_color	#FF0000
map_items_time_rings_color_bg	#FFFFFF
map_items_distance_rings_font_size	14.0
map_items_distance_rings_color	#C86400
map_items_distance_rings_color_bg	#FFFFFF
map_items_heading_line_color	#EC9000
map_items_heading_line_color_bg	#FFFFFF
map_items_course_bearing_line_color	#FA3232

map_items_course_bearing_line_color_bg	#FFFFFF
map_items_line_to_gps_font_size	14.0
map_items_line_to_gps_color	#009696
map_items_line_to_gps_color_bg	#FFFFFF
map_items_guiding_font_size	14.0
map_items_guiding_color	#009696
map_items_guiding_color_bg	#FFFFFF

Colorpicker

From:
<https://docs.locusmap.eu/> - Locus Map - knowledge base

Permanent link:
<https://docs.locusmap.eu/doku.php?id=manual:advanced:customization:config&rev=1432212965>

Last update: **2015/05/21 14:56**

