



Point alert

Available in Locus Map Pro only


What is it for?

This feature **notifies** you (with beeping, a custom sound, vibration or a voice phrase) when a point from a selected group is **nearby** (in the defined distance). Thanks to it, you don't have to check on the map all the time for geocaches near your hiking route, for example.

How to set it up?

1. Select points


- open **Folders** tab:



- check the **folder with points** you want to be **notified of**

2. Set distance and alarm frequency

- open **Basic** tab:




The screenshot shows the 'POI alert' settings screen with the 'BASIC' tab selected. The 'DISTANCE' is set to 500. Under 'TYPE OF NOTIFICATION', the 'Notify when new POI is in range' checkbox is checked, and 'Notify once' is selected with a radio button. The 'PAUSE BETWEEN NOTIFICATIONS' section has a text input field labeled 'Time (in seconds)'.

- **Distance** - set how far from the selected point Locus starts the alert
- **Notify when point is in range** - check to switch sound/vibration notifications on/off (visual notification on map stays on)
- **Notify once** - the alert goes on only once
- **Notify until stopped** - notification repeats in defined interval until stopped manually (red STOP button on screen) or when you're out of the alert distance.

3. Set type of notification

- open **Notification** tab:



The screenshot shows the 'POI alert' settings screen with the 'NOTIFICATION' tab selected. Under 'SETTINGS OF SOUND', 'Beep' is selected with a radio button, and the 'Number' is set to 1. There are buttons for 'PLAY' and 'SELECT SOUND'. Under 'SETTINGS OF VIBRATION', 'Disable' is selected with a radio button, and there is a 'Pattern' section with a 'PLAY' button and a help icon.

Settings of sound


- **Disable** - all sounds are disabled, only screen and vibration alert work
 - **Beep** - select number of beeps (1-10)
 - **Select sound** - select any sound stored in your device memory
 - **Text-to-speech** - enables voice prompts notifying of the name, distance, and direction of the point
- Tap **Play** to check your sound settings.

Settings of vibration

Visible only when the vibrator is present (mainly in mobile phones)

- **Disable** - the device does not vibrate on notifications
 - **Pattern** - set notification vibrating pattern, using three symbols: '.' for 200 milliseconds vibrations, '-' for 500 milliseconds vibrations and ' ' (space) for 500 milliseconds of silence.
- Tap **Play** to check your vibration settings.

4. Tap START in the topbar



Point alert does not notify of [LoPoints](#).

From:
<https://docs.locusmap.eu/> - Locus Map Classic - knowledge base

Permanent link:
https://docs.locusmap.eu/doku.php?id=manual:user_guide:functions:poi_alert&rev=1581074532

Last update: 2020/02/07 11:22

