



Image map calibration

About

This feature enables calibrating of an image of map and placing it over a background map. For example when you go to the ZOO or a park simply take a picture of its detailed plan displayed on a board at the entrance. After that you can calibrate the photo according to your background map and use it for your further navigation. **This option is available only to Locus Map Pro users.**

1. Get a map picture

- open the function in **Menu > More functions > On-board Map Calibrator**, a dialog appears
- tap **Take** to take a photo with you phone camera - the more quality camera, the better
- or **Select** to choose the photo from your device memory, from Dropbox etc.




We recommend to **copy the image** from your PC/scanner/internet or a DSLR camera to your Dropbox or the phone memory before selecting it to get better results

2. Calibrate the map picture

- tap *Add* and choose a **distinct point** (a hill summit, crossroads etc.) on your picture




- tap  in *Map coordinates menu* and choose **the same point** on your background map




- repeat this procedure **4 times** - try to select points making a rectangle. You can edit their

positions by tapping  or remove them.




3. Generate your calibrated map

- when you are ready with your four points the status line **turns green** and the *Create* button activates



- calibration points overview appears - indicates their **deviation**.



When it is not too significant you can name the new map and proceed to its rendering




If you have chosen a big image it is highly recommended to check **Optimize map** to divide the map image into many small maps (tiles) bundled into one file.

Save the calibration configuration for later use

If you have **more map images of the same size and scale** to calibrate you can use one configuration for calibrating them all:

1. calibrate the first image
2. **save the calibration configuration:**




3. open the next image
4. **load saved calibration** (topbar menu as well)
5. calibrate
6. repeat ad hoc.

4. Use the calibrated map



Your calibrated map appears now as an **overlay**



and can be managed in **Map Items** box or in the left panel **Active items** tab.



You can change opacity of the calibrated map by selecting it and moving the opacity slider:



Last
update: 2018/12/10 17:13 manual:user_guide:maps_tools:calibrator http://docs.locusmap.eu/doku.php?id=manual:user_guide:maps_tools:calibrator&rev=1544462037

From:
<http://docs.locusmap.eu/> - **Locus Map Classic - knowledge base**

Permanent link:
http://docs.locusmap.eu/doku.php?id=manual:user_guide:maps_tools:calibrator&rev=1544462037

Last update: **2018/12/10 17:13**

